

Object Detection

Object Detection

- 1. Model Introduction
- 2. Target Prediction: Images
 - Effect Preview
- 3. Target Prediction: Videos
 - Effect Preview
- 4. Target Prediction: Real-time Detection
 - 4.1. USB Camera
 - Effect Preview
 - 4.2. CSI Camera
 - Effect Preview
- References

Use Python to demonstrate **Ultralytics**: Object Detection effects on images, videos, and real-time detection.

1. Model Introduction

Object detection is a task that involves identifying the location and class of objects in images or video streams.

The output of an object detector is a set of bounding boxes that surround objects in the image, along with class labels and confidence scores for each box. If you need to identify objects of interest in a scene but don't need to know the exact position or precise shape of the objects, then object detection is a good choice.

2. Target Prediction: Images

Use yolo26n_ncnn_model to predict images in the ultralytics26 folder.

Enter the code folder:


```
cd /home/sunrise/ultralytics26/yahboom_demo
```

Run the code:

```
python3 01.detection_image.py
```

Effect Preview

yolo recognition output image location: /home/sunrise/ultralytics26/output/



Example code:

```
from ultralytics import YOLO

# Load a model
model = YOLO("/home/sunrise/ultralytics26/yolo26n_ncnn_model")
# model = YOLO("/home/sunrise/ultralytics26/yolo26n.pt")

# Run batched inference on a list of images
results = model("/home/sunrise/ultralytics26/assets/bus.jpg") # return a list
of Results objects

# Process results list
for result in results:
    boxes = result.boxes # Boxes object for bounding box outputs
    # masks = result.masks # Masks object for segmentation masks outputs
    # keypoints = result.keypoints # Keypoints object for pose outputs
    # probs = result.probs # Probs object for classification outputs
    # obb = result.obb # Oriented boxes object for OBB outputs
    result.show() # display to screen
    result.save(filename="/home/sunrise/ultralytics26/output/bus_output.jpg") #
    save to disk
```

3. Target Prediction: Videos

Use yolo26n_ncnn_model to predict videos in the ultralytics26 folder (not videos that come with ultralytics).

Enter the code folder:


```
cd /home/sunrise/ultralytics26/yahboom_demo
```

Run the code:

```
python3 01.detection_video.py
```

Effect Preview

yolo recognition output video location: /home/sunrise/ultralytics26/output/



Example code:

```
import cv2
from ultralytics import YOLO

# Load the YOLO model
model = YOLO("/home/sunrise/ultralytics26/yolo26n_ncnn_model")
# model = YOLO("/home/sunrise/ultralytics26/yolo26n.pt")

# Open the video file
video_path = "/home/sunrise/ultralytics26/videos/people_animals.mp4"
cap = cv2.VideoCapture(video_path)

# Get the video frame size and frame rate
frame_width = int(cap.get(cv2.CAP_PROP_FRAME_WIDTH))
frame_height = int(cap.get(cv2.CAP_PROP_FRAME_HEIGHT))
fps = int(cap.get(cv2.CAP_PROP_FPS))

# Define the codec and create a Videowriter object to output the processed video
output_path = "/home/sunrise/ultralytics26/output/01.people_animals_output.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width, frame_height))

# Loop through the video frames
while cap.isOpened():
    # Read a frame from the video
    success, frame = cap.read()

    if success:
        # Run YOLO inference on the frame
        results = model(frame)
```

```
# visualize the results on the frame
annotated_frame = results[0].plot()

# Write the annotated frame to the output video file
out.write(annotated_frame)

# Display the annotated frame
cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

# Break the loop if 'q' is pressed
if cv2.waitKey(1) & 0xFF == ord("q"):
    break
else:
    # Break the loop if the end of the video is reached
    break

# Release the video capture and writer objects, and close the display window
cap.release()
out.release()
cv2.destroyAllWindows()
```

4. Target Prediction: Real-time Detection

4.1. USB Camera

Use yolo26n_ncnn_model to predict USB camera footage.

Enter the code folder:


```
cd /home/pi/ultralytics26/yahboom_demo
```

Run the code: Click on the preview screen, press q key to terminate the program!

```
python3 01.detection_camera_usb.py
```

Effect Preview

yolo recognition output video location: /home/pi/ultralytics26/output/



Example code:

```
import cv2
from ultralytics import YOLO

# Load the YOLO model
model = YOLO("/home/sunrise/ultralytics26/yolo26n_ncnn_model")
# model = YOLO("/home/sunrise/ultralytics26/yolo26n.pt")

# Open the camera
cap = cv2.VideoCapture(0)
cap.set(6, cv2.VideoWriter_fourcc('M', 'J', 'P', 'G'))
cap.set(cv2.CAP_PROP_FRAME_WIDTH, 640)
cap.set(cv2.CAP_PROP_FRAME_HEIGHT, 480)

# Get the video frame size and frame rate
frame_width = int(cap.get(cv2.CAP_PROP_FRAME_WIDTH))
frame_height = int(cap.get(cv2.CAP_PROP_FRAME_HEIGHT))
fps = int(cap.get(cv2.CAP_PROP_FPS))

# Define the codec and create a Videowriter object to output the processed video
output_path = "/home/sunrise/ultralytics26/output/01.detection_camera_usb.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v') # You can use 'XVID' or 'mp4v'
depending on your platform
out = cv2.VideoWriter(output_path, fourcc, fps, (frame_width, frame_height))
```



```

# Loop through the video frames
while cap.isOpened():
    # Read a frame from the video
    success, frame = cap.read()

    if success:
        # Run YOLO inference on the frame
        results = model(frame)

        # Visualize the results on the frame
        annotated_frame = results[0].plot()

        # Write the annotated frame to the output video file
        out.write(annotated_frame)

        # Display the annotated frame
        cv2.imshow("YOLO Inference", cv2.resize(annotated_frame, (640, 480)))

        # Break the loop if 'q' is pressed
        if cv2.waitKey(1) & 0xFF == ord("q"):
            break
    else:
        # Break the loop if the end of the video is reached
        break
# Release the video capture and writer objects, and close the display window
cap.release()
out.release()
cv2.destroyAllWindows()

```

4.2. CSI Camera

Use yolo26n_ncnn_model to predict CSI camera footage.

Enter the code folder:

```
cd /home/sunrise/ultraalytics26/yahboom_demo
```

Run the code: Click on the preview screen, press q key to terminate the program!

```
python3 01.detection_camera_csi.py
```

```


ID Read: 0x00
WARN: Sensor Name: sc035hgs-vc0, Expected Chip ID: 0x35, Actual Chip ID Read: 0x
00
WARN: Sensor Name: sc035hgs-vc1, Expected Chip ID: 0x35, Actual Chip ID Read: 0x
00
WARN: Sensor Name: sc231ai-30fps, Expected Chip ID: 0xCB6A, Actual Chip ID Read:
0x00
plase choose sensor config,the number should small than 3

```

When this prompt appears in the running terminal, press 2, then press Enter,

Effect Preview

yolo recognition output video location: /home/sunrise/ultralytics26/output/



Example code:

```
import cv2
from SunriseRobotLib import Mipi_Camera

from ultralytics import YOLO

width=640
height=480
g_camera = Mipi_Camera(width, height, debug=False)

# Load the YOLO model
model = YOLO("/home/sunrise/ultralytics26/yolo26n_ncnn_model")
# model = YOLO("/home/pi/ultralytics26/yolo26n.pt")

# Set up video output
output_path = "/home/sunrise/ultralytics26/output/01.detection_camera_csi.mp4"
fourcc = cv2.VideoWriter_fourcc(*'mp4v')
out = cv2.VideoWriter(output_path, fourcc, 30, (640, 480))

while True:
    # Capture frame-by-frame
    ret, frame = g_camera.read()
```

```
frame = cv2.resize(frame,(640,480))

# Run YOLO11 inference on the frame
results = model(frame)

# Visualize the results on the frame
annotated_frame = results[0].plot()

# Write the frame to the video file
out.write(annotated_frame)

# Display the resulting frame
cv2.imshow("Camera", annotated_frame)

# Break the loop if 'q' is pressed
if cv2.waitKey(1) == ord("q"):
    break

# Release resources and close windows
g_camera.release()
out.release()
cv2.destroyAllWindows()
```

References

[Object Detection - Ultralytics YOLO Documentation](#)